

## **WPA-PSK Configuration of Cisco 1130 Autonomous Access Point**

### **Objective 1 : Setting Up the Access Point Base Configuration**

#### **Step 1**

Define the hostname for the access point. In this scenario, we will configure this access point hostname as “**Ap**”

**Ap#configure terminal**

**Ap(config)# hostname Ap**

#### **Step 2**

Define the local username and password for access point level 15 management. In this scenario, we will use the username of “**admin**” and the password of “**password**”.

**Ap(config)# username admin privilege 15 password password**

### **Objective 2 : Configuring Access Point Radio Interface**

Activate access point radio interface, define the SSID, encryption mode and specify VLAN number to be bind with the encryption mode. In this scenario, we will use “MyWireless” as the SSID and VLAN 1.

**Ap(config)# interface Dot11Radio0**

**Ap(config-if)# no shutdown**

**Ap(config-if)# encryption mode ciphers tkip**

**Ap(config-if)# encryption vlan 1 mode ciphers tkip**

**Ap(config-if)# ssid MyWireless**

## **Configuring Access Point in Global Configuration Mode**

Create SSID in global configuration mode and attached it to the radio interface. Input the command below to allow access point to broadcast SSID with WPA Pre-shared key of “abcd1234”

```
Ap(config)# dot11 ssid MyWireless
Ap(config-ssid)# vlan 1
Ap(config-ssid)# authentication open
Ap(config-ssid)# authentication key-management wpa
Ap(config-ssid)# guest-mode
Ap(config-ssid)# wpa-psk ascii abcd1234
```

## **Objective 4 : Configuring Radio Sub-Interface to Bind with Bridge Interface**

Configure radio sub-interface to associate with bridge virtual interface. Enable encapsulation dot1q to bind with VLAN number.

```
Ap(config)# interface Dot11Radio0.1
Ap(config-subif)# encapsulation dot1Q 1 native
Ap(config-subif)# bridge-group 1
```

## **Objective 5 :Configuring IP Address for Bridge Virtual Interface**

Assign IP address for bridge virtual interface. In this scenario, we will use the IP address of 192.168.1.10 /24 . Configure the default gateway IP address of 192.168.1.1 /24

```
Ap(config)# interface bvi 1
Ap(config-if)# ip address 192.168.1.10 255.255.255.0
Ap(config)# ip default-gateway 192.168.1.1
```

All product names used herein, are trade names, service marks, trademarks, or registered trademarks of their respective owners.  
www.network-insider.net and "Cisco VPN Reference Guide for Field Engineers" are not associated with any product or vendor mentioned,  
including Cisco Systems. Cisco Routers are registered trademarks of Cisco Systems, Inc.  
Copyright © network-insider.net 2010, All Rights Reserved